

Installing FUTURA 4.0.0.6 Update for Windows 8

Installation Instructions: For models: XL-400; XL-550; FQ-4; SEQS-6000; SEQS-6700.

1. Attach embroidery unit to machine, connect USB cable to machine and computer (Turn machine OFF).
2. Download update and save to desktop.
3. Place base software CD in tray.
4. Allow installation.
5. Pop up will tell you it will install drivers (Make sure the machine is turned off).
6. Click OK.
7. It will ask to install Jungo - say yes.
8. It will ask to play tutorial - say no.
9. Run update from your desktop.
10. Windows 8 will display "Windows smart screen prevented an unrecognized app from starting".
Select "More Info".
11. Click on Run Anyways.
12. Follow prompts.
13. Pop up will appear asking "Would you like to install this device?"
14. Place a check mark in "Always trust software from Jungo Ltd".
15. Click install.
16. It will ask "Would you like to install this device software?"
17. Place a check mark in "Always trust software from Compucon".
18. Click Install.
19. Turn ON machine.
20. Open software (program should open).
21. Close software.
22. If you own any options, load options and follow prompts.
23. Once options are loaded, open software, you should now be able to view options from the create menu.

SINGER is sewing made easy.™